



XEROX 7800 PHASER
ADOBE PHOTOSHOP
(ADDM_PHASER, ADDM_CARDSTOCK)

XEROX 7800 Specs.

Cut-sheet size - 5.8" x 8.3" up to 11" x 17"


PHOTOSHOP PREP (COLOR)

Laserjet Printing with a Color-Managed Workflow

Open your file in Photoshop if you haven't already.


1. Set Mode and Image Size

Make sure your image is sized correctly (the size you want to print it) and the resolution is set to 240 dpi (Image > Image Size...). Use the Image Size window to define the size of the image area of your print. Make sure to change your image size in inches--never in pixel dimensions! If you uncheck "Resample," the printing resolution will change independent of the number of pixels representing the image in width and height. *On most paper, there is little to be gained by printing a resolution higher than 240 pixels/inch.* Your image will begin to be visibly soft as you drop down below 100 pixels/inch.




2. Set correct Color Profile

- a. Make sure your file is set to Working CMYK-US Web Coated (Swop) V2. Open the Convert to Profile window (Edit > Convert to Profile...). Under "Destination Space," select Working CMYK-US Web Coated (Swop) V2.




2. Send it to print!

- a. Your file is now ready to print. Take care to manage the following print settings. Open the Photoshop Print Settings dialogue box (File > Print).



- b. Under “Printer Setup,” select ADDM-PHASER for laser jet paper or ADDM-CARDSTOCK for cardstock. Then open the Print dialogue box by selecting “Print Settings...”



-Choose Paper Size:
'US Letter' or 'Tabloid'

Click the Layout drop down menu in the middle of the Print dialogue box and select Xerox Features

c. Under Xerox Features, Paper / Output, adjust the following settings:


Job Type: Normal Print

Paper: Choose 'Plain' for laserjet paper or 'Cardstock' if you're interested in printing on cardstock.

2-Sided Printing: Choose 1-Sided Print or 2-Sided Print depending on your file.


Print Quality: Choose Enhanced for graphics or Photo Mode for photographs.

Output Destination: Automatically Select



If you want to make any color adjustments through the printer driver, click the Paper / Output drop down menu at the top of the Xerox Features dialogue box and select Color Options.


For Color Correction, choose Automatic or Black and White. You can also select Custom Color Options, which will open a new window. Select the Color Adjustment panel for additional color corrections.



OK

SAVE

Now you can preview your image and manage just a few more settings.



- c. After clicking SAVE, you'll be brought back to the Photoshop Printer Settings dialogue box. Under "Printer Setup," choose how many copies you want. Printing one is suggested before making multiple copies.
- d. Select the appropriate Layout for your image, whether it is a portrait or a landscape.
- e. Under "Color Management," select the following settings:

Color Handling: Printer Manages Colors

Rendering Intent: Perceptual or Relative Colorimetric, depending on what you chose in soft proofing

PRINT